

# **Flash Flood Monitoring and Prediction (FFMP)**

## **Guide for Users**

version OB5

December 7, 2004

Tom Filiaggi

Decision Assistance Branch - HydroMet Monitoring

NWS - MDL

# Table of Contents

Table of Contents .....	2
<a href="#">Introduction</a> ↵ .....	3
<a href="#">What's New in OB5?</a> ↵ .....	3
<a href="#">Requesting the FFMP Suite</a> ↵ .....	4
<a href="#">The D2D</a> ↵ .....	4
<a href="#">The FFMP Basin Table Constituents:</a> ↵ .....	4
<a href="#">The Menu/Information Bar</a> .....	4
<a href="#">The Options Buttons</a> .....	5
<a href="#">The Attribute Title Row</a> .....	8
<a href="#">The Table Body</a> .....	8
<a href="#">The Inspection Row</a> .....	9
<a href="#">FFMP Basin Table Sub-GUIs in Detail</a> .....	9
<a href="#">Attribute Color Threshold (ACT) Window</a> .....	9
<a href="#">Basin Trend Graph</a> ↵ .....	9
<a href="#">FFMP Flash Flood Guidance</a> ↵ .....	10
<a href="#">FFMP Flash Flood Threat Index (FFTI)</a> ↵ .....	10
<a href="#">FFMP's Forced Flash Flood Guidance GUI</a> ↵ .....	10
<a href="#">Data Monitoring System (DMS)</a> ↵ .....	11
<a href="#">Figures</a> ↵ .....	13
<a href="#">Help</a> ↵ .....	17
<a href="#">Glossary</a> ↵ .....	17
<a href="#">Appendices</a> .....	18

## Introduction [←](#)

The Flash Flood Monitoring and Prediction (FFMP) system is an integrated suite of multi-sensor applications which detects, analyzes, and monitors precipitation and generates short-term warning guidance for flash flooding automatically within AWIPS. FFMP will provide forecasters with accurate, timely, and consistent guidance and supplement forecaster event monitoring with multi-sensor, automated event monitoring. The intended benefits are:

- ☺ Longer lead times on warned events
- ☺ Fewer missed events
- ☺ Increased forecaster situational awareness
- ☺ Reduced forecaster fatigue during warning situations

## Service Backup

FFMP was initially designed to conduct its analyses using data from only those radars defined as dedicated in AWIPS (ie: had a dedicated hard-line to the radar). Now, FFMP utilizes a text file to tell it which radars to acknowledge and which CWAs to analyze. This file is \$FXA\_DATA/tstorm/FFMPPradarToCWA.txt and contains explanations of its format.

If you want FFMP to analyze a radar that is **not** dedicated, **after** providing the radar's identifier in the file, you must:

- Ensure that you have the small basin and bin shapefiles for the non-dedicated radar in the proper directory,
- Run a -scan localization after editing the FFMPPradarToCWA file,
- Use the Radar Multi-Request (RMR) method of ingesting the DHR from other radars. You can find information on the RMR in the AWIPS User's Manual.

This implies that you must know in advance what radar's you think will be of interest, as FFMP will only **start** its accumulations when it begins to receive those RMR-requested data. It is understood that you cannot predict Service Backup incidents, so it would be prudent to set up your FFMPPradarToCWA file with any potential radars, ensure all necessary shapefiles are properly available, and localizations have been successfully run. Then use the RMR any time an event is expected for a non-dedicated radar of interest.

This will effectively cover Service Backup CWAs. You will see that the SCAN menu contents look different, but the organization should be intuitive.

## What's New in OB5? [←](#)

- [Aggregated Layers](#): FFMP will now allow you to display automatically aggregated layers of small basins. Note that all FFMP displays are now considered layers - even the county display.

- Point Data Control (PDC): FFMP now provides a PDC GUI that looks and feels like the PDC GUI from HydroView. The PDC allows you to display point data from the Hydro data base as overlays in the D2D. See the HydroView PDC documentation.
- [Service Backup](#): You can now tell FFMP what radars to recognize and use via a text file. You will have to utilize the RMR to fully enable this feature.
- [Stream Links Map](#): There is another FFMP map available that shows the ‘realistic’ stream channels, without all of the clutter of the ‘small basin’ channels.
- Start-up bug fix: Occasionally, the FFMP would fail to start in OB4. This has been fixed and *may* make it into an OB4 Maintenance Release. If not, it has been fixed for OB5.

## Requesting the FFMP Suite ↩

Under the SCAN menu there are sections for each dedicated radar. Each of these radar sections has the available FFMP products (as well as other SCAN products).

FFMP consists of a flexible image display and a Graphical User Interface (GUI), called the Basin Table. To load FFMP, select “FFMP Image / Basin Table” for the radar of interest. This will load the FFMP Small Basin image in the D2D and load the Basin Table GUI (but will not load any FFG data). A small loading image will appear on the lower left part of the screen while the Basin Table GUI is being created. If there is no data to display, you will be informed and FFMP will not load.

Note that FFMP has several of its own **maps** under the D2D Maps menu. This includes the new Stream Links map, which shows realistic stream beds.

## The D2D ↩

Once FFMP is loaded, on the D2D you will see a county map. If sufficient precipitation has fallen in the specified time frame, the counties in the CWA will be color-filled. The small legend in the upper left corner of the pane will display the time frame (in hours) and attribute used to create the display. The Basin Table will appear on top of the D2D. ([See Figure 1](#))

## The FFMP Basin Table Constituents: ↩

[See Figure 1.](#)

### The Menu/Information Bar

Contains the File Menu and information regarding the link to the D2D and the valid time of the

FFMP Basin Table.

## The File Menu

Retrieve Default Configuration	Retrieves and uses the default basin configuration file.
Retrieve Configuration...	Retrieves and uses a specified basin configuration file.
Save Configuration	Saves the basin configuration file.
Save Configuration As...	Saves the basin configuration file to a new file, defined by the user.

## Link to Frame

Indicates whether the valid time in the FFMP Basin Table will always match the time in the D2D frame. If this button is activated and the user changes the frame in the D2D, the basin table will update to match the data shown on the D2D. If this is off, the data in the basin table will represent the *most recent inventory time*.

## Ending Time

This displays the UTC time for which the data in the basin table is valid. This is the beginning of the volume scan for which the pertinent time duration ends.

## The Options Buttons

Below the Menu/Information bar and above the body of the basin table.

## Refresh D2D

This button will allow the D2D to see any changes made to the way data is displayed in the Basin Table, thus updating the D2D image to reflect the data in the Basin Table. For example, if you wish to change the duration in the D2D FFMP image, you first change the duration in the basin table (see below), then click the Refresh D2D button and the image in the D2D will change its duration to what was just selected in the Basin Table. This button will change color if something has changed in the Basin Table that would require the FFMP display in the D2D to be updated in order for the two display components to agree.

## Display Rate

Normally, FFMP will display either precipitation accumulation or a comparison between the accumulation and FFG (see Thresh Type below), in the D2D. However, FFMP can also display ‘instantaneous’ rate data, according to county and basin. If you wish to view this, toggle the ‘Display Rate’ button on by clicking it, then click the ‘Refresh D2D’ button. Repeat these steps to turn it off.

## Thresh Type

Both the basin trends ([see below](#)) and the D2D FFMP images are color-coded based on the type of threshold the user wants to view. The choices of threshold type are: precip (accumulation), diff (accumulation minus FFG), and ratio (accumulation divided by FFG). This button displays the current threshold type chosen. If you wish to change this, click on this button and make a different selection. The Basin Table will update. If you wish to have the D2D update as well, click the Refresh D2D button (as described [above](#)).

## Data Sources

This menu button lists all precipitation data sources available for use in the table. The precipitation source selected is used in computing the ratio and difference values in the table. Digital Hybrid Reflectivity (DHR) radar product is the primary precipitation source for the FFMP table and display, but several other sources are available, including SCAN 1-Hour QPF, and several other QPF and QPE options. Note that the selection of these additional precip sources will not affect FFMP's background precipitation monitoring. FFMP will continue to tabulate precipitation totals based on the DHR product. Note also that, except for the SCAN 1-Hour QPF, the displays for these extra sources will not auto-update; they must be re-selected to refresh.

## Ag Lvl

The Aggregation Levels button reflects what kind of data is being listed in the table and displayed in the D2D. In earlier versions of FFMP, there were only 2 display choices: County and Basin, and the Basin choice meant only those basins in a zoomed-in County. Now, all display choices are considered layers - aggregated layers - and when you choose the “All & Only Small Basins”, you will see just that in the D2D and Basin Table, all small basins and only small basins (no aggregation) no matter the zoom. In addition to these two basic choices, there are also several automatically aggregated layers, starting at the HUC level (large basins, much aggregation) and going down in spatial scale (smaller basins, little aggregation). This aggregation is automatic, hydrologically sound, and based on the Pfafstetter codification scheme. In the future, we expect to allow user-defined ARC GIS shapefiles and ingest them as user-defined aggregated layers.

Note: when you choose a layer, you do not have to click the “Refresh D2D” button, so choose with the expectation that the display may take a second or two to update itself.

## Zoom Behavior

With the implementation of Auto-Aggregated Layers, we needed to provide a bit more flexibility, so we could sustain legacy functionality and provide additional customization. The best thing to do in order to learn how these settings behave is to play around with the “Maintain Layer” and “Only Basins in Parent” buttons. But if you want some guidelines, here they are:

Maintain Layer	Only Basins in Parent	Description
OFF	ON	These are the legacy settings, which means that the FFMP Zoom Behavior will be the same as it has been before the implementation of Auto-Aggregated Layers. When you click on an Area_Id in the <a href="#">Table Body</a> , the Zoom and Recenter function will zoom into that area in the D2D and display only those small basins that exist in the parent area you just zoomed in on, but not any small basins outside that area of interest.
OFF	OFF	Both settings off means that when you zoom in on an area, you will see all small basins within the field of view. Take care in using this, as when you zoom in you may find it hard to see your landmarks (and county boundaries) and you may lose where you are.
ON	OFF	These settings mean, when you zoom in on an area, you will not see any small basins at all, but will see all areas of your chosen Aggregation Level in the field of view. You will continue to see whatever layer you have chosen from the <a href="#">Ag Lvls</a> menu.
ON	ON	These settings are not really of any use. With these, when you zoom in on an area, you will only see that area and not any small basins.
<b>Override</b> If you have chosen the “All & Only Small Basins” from the <a href="#">Ag Lvls</a> menu, you will always see all and only small basins in the D2D and in the Basin Table, effectively overriding anything set in the “Maintain Layer” and “Only Basins in Parent” toggles.		

## Group Label

The wide button above the Area\_Id column title is the Group Label button. This will tell you if you are viewing a Group List (a list of areas, be they counties, small basins, or a HUC Layer) or if you are viewing the small basins after executing a Zoom and Recenter action. For example: the user started with the County Layer (which is default) and has clicked on one county, which zooms and recenters in the D2D and displays a list of small basins in that chosen County. After they zoom and recenter, the Group Label will show the name of that county chosen and, if clicked, will zoom back out and return to that county list.

## Durations

The raw FFG received from the RFCs exists for the one, three, and six hour time duration. From these base values, FFG can be interpolated or extrapolated to other time frames. A new time frame can be chosen by clicking on the “Duration” button and selecting one of the durations listed. Once one of the durations is selected, the current table will be updated to display the data only for the new requested duration without destroying the entire window. The current duration is printed on the “Durations” button.

## **The Attribute Title Row**

Shows (in black) what attributes are available for viewing. When the cursor is focused over these titles, a tip text pop-up will appear, describing what button click actions will trigger what functionality. See [Appendix A](#) for some additional information on these attributes.

### **Ranking By Attribute**

Clicking on applicable attribute titles will sort the table data according to that attribute. A purple attribute button background color signifies that this attribute was the last attribute to be used for sorting the table data. Refer to [Appendix A](#) to see for which attributes the table can be ranked.

### **Changing the Attribute Color Thresholds**

Clicking Button 3 on applicable attribute titles will bring up the Attribute Color Threshold (ACT) window. The ACT window allows the user to define value ranges of each applicable basin attribute. These value ranges are intended to reflect the degree of strength of the attributes, from green (weak) to yellow (moderate) to red (strong). Refer to [Appendix A](#) to see which attributes can be multi-colored.

## **The Table Body**

Displays the basin or county information, including such attributes as precipitation estimate and comparisons to Flash Flood Guidance. If there is no rainfall over all geographic entities for the specified precipitation data source and time duration, the data presented in the table will have error values (ie: “na”). The values for the various basin attributes are displayed in the table body and color coded (when applicable) according to the attribute color thresholds defined in the ACT window. Also, when the cursor focuses over an area identifier, the full name of the area will appear in a text pop-up box. Refer to [Appendix A](#) for a list of all basin attributes available through FFMP. Note that for Virtual Gage Basins, the basin Id begins with the letter G, whereas all other basin have numeric identifiers only.

### **Inspecting a Basin or County**

Clicking on an identifier in the ‘area\_Id’ column will cause the D2D to zoom-and-recenter on that particular county or basin. If the list is a county list, the D2D will zoom in on that particular county and display the basins within that county only, and the data for the basins within that county will be listed in the Basin Table. If the list is a basin list, the D2D image will zoom in



further than the zoom for a county, fill the Inspection Row with data for that basin, and highlight that basin's identifier in the 'area\_Id' column. The Inspection Row can be seen in [Figure 1](#).

## The Inspection Row [←](#)

Duplicates the row in the table body for the basin that was last inspected (see the section on basin inspection under the [Table Body](#) topic for instructions on how to inspect a basin). This row emphasizes the data for the identified basin last inspected via the zoom-and-recenter method. The individual grid boxes in the Inspection Row have the same capabilities as the grid boxes in the table body, except clicking on the identifier box will zoom the D2D back out to the zoom level defined on the D2D menu bar. [See Figure 1](#).

## Zooming Back Out

Clicking on the identifier in the 'area\_Id' column will cause the D2D to zoom back out (after zooming in on a basin) to the single-county view, but retain the basin listing in the Basin Table.

## FFMP Basin Table Sub-GUIs in Detail [←](#)

### Attribute Color Threshold (ACT) Window

Launched from the Attribute Title Row. The user can edit the color-coded strength values for any of the basin attributes displayed in the Attribute Title Row.

"Attribute:"	The user can switch to a different basin attribute. The units of the attribute will also appear on this button.
"Upper:", "Mid:", "Lower:"	The strength thresholds, corresponding to the attribute values that meet or exceed these threshold values.
"Apply"	The user accepts the changes just made and closes the window.
"Cancel"	The user can discard the changes just made.

## Basin Trend Graph [←](#)

A Basin Trend Graph can be produced by clicking Button 3 on the basin identifier (for a basin list). It can also be produced by enabling the "FFMP Table Display" in the D2D (click Button 3 on the legend of the same title) and clicking Button 3 over a basin. The way the data is displayed in the Basin Trend Graph may take a bit of time to get used to. Here's an example of interpretation for the "3.0" point on the x axis: the rate plot represents the instantaneous precipitation rate for the volume scan with beginning time of 3.0 hours in the past; the accumulation plot represents the amount of precipitation that has fallen in the past 3.0 hours; the FFG plot represents the Flash Flood Guidance valid for the 3.0-hour time frame. The gage plot

represents comparable gage precipitation accumulation data (only for Virtual gage Basins). The colors under the accumulation plot represent the degree of urgency with which the basin should be investigated. The color thresholds and the attribute to which the thresholds will be applied are presented in the color legend at the bottom of the GUI and can be chosen via the ACT window and the Threshold Type Selector, both available in the Basin Table itself. See [Figure 2](#) for an example of a Basin Trend.

## FFMP Flash Flood Guidance [←](#)

The FFMP provides a D-2D display of the gridded Flash Flood Guidance data issued by the River Forecast Centers (RFCs). This is the same data that is currently available in the Surface menu (under “RFC FFG/QPE/QPF images”). While the Surface menu selection will let you choose FFG data from individual RFCs or a national mosaic, the FFMP display will mosaic data from all RFCs that have coverage over the local small stream basins. Instead of using a single inventory time, the FFMP display will mosaic the latest FFG data from the selected RFCs, even if the inventory times are different, provided that the data is no older than 36 hours.

## FFMP Flash Flood Threat Index (FFTI) [←](#)

Under the WarnGen button on the D2D, there are several buttons. One, marked by “FF” is the FFMP Flash Flood Threat Indicator. The color of the FFTI indicator will represent the value of the chosen attribute. The attributes to choose from are: precipitation accumulation derived from the DHR radar product (“dhr”), the ratio of the precipitation accumulation to the FFG, and the difference between the precipitation accumulation and FFG. You may choose which attribute and what time frame to monitor and the color thresholds used for the FFTI button by clicking on the “FF” button. This will bring up the FFTI Change GUI ([see Figure 3](#)). If you place the mouse cursor over this button, some text will pop-up, providing some additional information, such as what is being monitored and for what time frame.

The colors and what they represent are:

- ★ **White** indicates little or no activity in the CWA.
- ★ **Green** indicates precipitation in the CWA.
- ★ **Yellow** indicates moderate precipitation estimates in the CWA.
- ★ **Red** indicates heavy precipitation estimates in the CWA.
- ★ **Grey** indicates an invalid index number, which means the FFMP processor is not behaving properly or data is missing.

You may also define how old ‘too old’ is for FFG to be used in FFMP. Simply enter the number of hours in the provided entry field.

## FFMP’s Forced Flash Flood Guidance GUI [←](#)

We have provided a GUI with which you can provide your own FFG values. The Forced FFG GUI has its own, separate User's Guide.

## Data Monitoring System (DMS) [←](#)

The FFMP Data Monitoring System (DMS) is a web browser-based, automated system for monitoring the status of the vital components of FFMP. It consists of a suite of HTML files, a Tcl/Tk Common Gateway Interface (CGI) script, and various supporting procedure, data, and image files. The system is housed on a web server, accessed through any browser that supports frames, and is updated using the CGI script. The following information is intended to give an overall description of the system display, defining the layout and components, and provide instructions for using the system.

### DMS Display

[\*See Figure 4.\*](#)

The FFMP DMS display is divided into two frames. A small, static frame at the top of the page holds the title information and the button for updating the table information. The main frame below houses the data monitoring graphical elements.

#### Radar Products Information Table

The Radar Products Information table monitors the status of the DHR radar product for each dedicated radar. For each dedicated radar, the monitor reports whether or not the DHR product is on the Routine Products Set (RPS) list (Y for Yes, N for No), and gives the most recent GMT inventory time. If the DHR product is absent from the RPS list, the background of the table cell containing the letter "N" will be colored red. If the DHR product is not available, meaning there is no data file in the directory where it is stored, the monitor reports "None" and colors the background of the table cell red. Similarly, if a data file time is old, the background of the cell is colored red. A file is determined to be old according to a formula derived from the VCP mode (twice the length of the volume scan plus 2 minutes). If the VCP mode is not available, the default threshold value of 22 minutes is used.

#### Flash Flood Guidance Information Table

The FFG Information table monitors the status of FFG products for each River Forecast Center (RFC) that has responsibilities within the WFO's CWA. For each time period, and for each RFC, the monitor reports the most recent GMT inventory time. If the product is not available, meaning there is no data file in the directory where it is stored, the monitor reports "None" and colors the background of the table cell red. Similarly, if a data file time is old, the background of the table cell is colored red. A file is determined to be old if it is older than 36 hours.

### Using the DMS


### **Loading the DMS**

The file name to enter into the browser address line is [http://as1f/infoPages/FFMP\\_DMS.html](http://as1f/infoPages/FFMP_DMS.html).

### **Updating the Information: Automatic and Manual**


In the static frame at the top of the display, there is a blue button labeled “UPDATE INFO.” Clicking this button will refresh the information displayed in the lower frame. Also, for convenience, the DMS is equipped with an automatic update feature. This feature allows the user “hands-free” monitoring, updating the information automatically every two minutes.

Figures ↵



**Figure 1** This shows the FFMP Basin Table and Button Color Threshold GUI with the D2D. The D2D shows the FFTI indicator below the WarnGen button. It also shows a view of the All & Only Small Basins layer.





**Figure 2** This is a Basin Trend. Please take time to examine this trend to fully understand what it is showing. The “Rate” plot represents the ‘instantaneous’ rate determined from the DHR radar products, backwards in time. The “Accum” plot represents the precipitation accumulation for the specified number of hours in the past to the most recent data time. The “FFG” plot is the valid Flash Flood Guidance for the specified time frame (not the number of hours in the past), thus the comparability to the accumulation plot. The “Gage Accum” plot is for a found gage in the basin and is provided in order to compare gage and radar precipitation estimates. Note that this image is for a Virtual Gage Basin. Regular Basin Trends would not contain a Gage Accum plot.



**Figure 3** This is the FFTI Change GUI, rendered by clicking on the “FF” button below the WarnGen button on the D2D.

File Edit View Go Communicator Help

WebMail People Yellow Pages Download New & Cool Channels

Bookmarks Netsite: [http://as1f/infoPages/FFMP\\_DMS.html](http://as1f/infoPages/FFMP_DMS.html) What's Related

**Welcome to the FFMP Data Monitoring System**

**UPDATE INFO**

*\* The page will automatically update every 2 minutes*

**Last Update Time: Aug 30, 2001 19:02:33 GMT**

Radar Products		Dedicated Radar	
		KLWX	KAKQ
DHR	On RPS List?	Y	N
	Most Recent File*	20010830_1854	None

Flash Flood Guidance		River Forecast Centers
		MARFC
1 Hour	Most Recent File*	20010830_1200
3 Hour	Most Recent File*	20010830_1200
6 Hour	Most Recent File*	20010824_1200

\* A red background indicates old data, or data that is not available (None).  
 Radar data is "old" 22 minutes after the beginning of the volume scan (time shown).  
 Flash Flood Guidance is "old" 36 hrs after the valid time.

**Figure 4** The FFMP web Data Monitor, showing the availability of the DHR product and Flash Flood Guidance from all sending River Forecast Centers.



## Help ↩

Please check the FFMP web page for more detailed info at <http://www.nws.noaa.gov/mdl/ffmp>. To report problems or ask questions concerning the operation of FFMP in general, please send e-mail to the FFMP list server ([awips-ffmp@infolist.nws.noaa.gov](mailto:awips-ffmp@infolist.nws.noaa.gov)).

## Glossary ↩

ACT - Attribute Color Threshold  
CGI - Common Gateway Interface  
CWA - County Warning Area  
D2D - Display 2 Dimensions  
DMS - Data Monitoring System  
DHR - Digital Hybrid Reflectivity  
FFMP - Flash Flood Monitoring and Prediction  
FFTI - Flash Flood Threat Indicator  
GUI - Graphical User Interface  
RFC - River Forecast Center  
RPS - Routine Products Set  
VCP - Volume Coverage Pattern

## Appendices

Appendix A FFMP Table Attributes for Counties and Basins

Attribute	Definition	Units	Can be used for ranking?	Can be multi-colored?
area_Id	County or Basin or Virtual Gage Basin Identifier	15 letter ID	Yes	No
rate	Single Volume Scan Precipitation Rate	Inches per Hour	Yes	Yes
precip	Average precip. for GeoArea.	Inches	Yes	Yes
ffg	Flash Flood Guidance	Inches	Yes	No
ratio	Ratio: precip. / FFG	%	Yes	Yes
diff	Difference: precip. - FFG	Inches	Yes	Yes